# **Cursor controll in PHP cli scripts**

Controll cursor in CLI scripts by echoing ANSI characters

### echo "\033[100D";

Many computer terminals and terminal emulators support colour and cursor control through a system of escape sequences. One such standard is commonly referred to as ANSI Colour. Several terminal specifications are based on the ANSI colour standard, including VT100.

The following is a partial listing of the VT100 control set.

<ESC> represents the ASCII "escape" character, 0x1B. Bracketed tags represent modifiable decimal parameters; eg. {ROW} would be replaced by a row number.

### **Device Status**

The following codes are used for reporting terminal/display settings, and vary depending on the implementation:

- Query Device Code <ESC>[c
  - Requests a Report Device Code response from the device.
- Report Device Code <ESC>[{code}0c
  - Generated by the device in response to Query Device Code request.
- Query Device Status <ESC>[5n
  - Requests a Report Device Status response from the device.
- Report Device OK <ESC>[0n
  - Generated by the device in response to a Query Device Status request; indicates that device is functioning correctly.
- Report Device Failure <ESC>[3n
  - Generated by the device in response to a Query Device Status request; indicates that device is functioning improperly.
- Query Cursor Position <ESC>[6n
  - Requests a Report Cursor Position response from the device.
- Report Cursor Position <ESC>[{ROW};{COLUMN}R
  - Generated by the device in response to a Query Cursor Position request; reports current cursor position.

## **Terminal Setup**

The h and I codes are used for setting terminal/display mode, and vary depending on the implementation. Line Wrap is one of the few setup codes that tend to be used consistently:

- Reset Device <ESC>c
  - Reset all terminal settings to default.
- Enable Line Wrap <ESC>[7h

- Text wraps to next line if longer than the length of the display area.
- Disable Line Wrap <ESC>[7]
  - Disables line wrapping.

### **Fonts**

Some terminals support multiple fonts: normal/bold, swiss/italic, etc. There are a variety of special codes for certain terminals; the following are fairly standard:

- Font Set G0 <ESC>(
  - Set default font.
- Font Set G1 <ESC>)
  - Set alternate font.

### **Cursor Control**

- Cursor Home <ESC>[{ROW};{COLUMN}H
  - Sets the cursor position where subsequent text will begin. If no row/column parameters are provided (ie. <ESC>[H), the cursor will move to the home position, at the upper left of the screen.
- Cursor Up <ESC>[{COUNT}A
  - Moves the cursor up by COUNT rows; the default count is 1.
- Cursor Down <ESC>[{COUNT}B
  - Moves the cursor down by COUNT rows; the default count is 1.
- Cursor Forward <ESC>[{COUNT}C
  - Moves the cursor forward by COUNT columns; the default count is 1.
- Cursor Backward <ESC>[{COUNT}D
  - Moves the cursor backward by COUNT columns; the default count is 1.
- Force Cursor Position <ESC>[{ROW};{COLUMN}f
  - Identical to Cursor Home.
- Save Cursor <ESC>[s
  - Save current cursor position.
- Unsave Cursor <ESC>[u
  - Restores cursor position after a Save Cursor.
- Save Cursor & Attrs < ESC > 7
  - Save current cursor position.
- Restore Cursor & Attrs <ESC>8
  - Restores cursor position after a Save Cursor.

## **Scrolling**

- Scroll Screen <ESC>[r
  - Enable scrolling for entire display.
- Scroll Screen <ESC>[{start};{end}r
  - Enable scrolling from row {start} to row {end}.
- Scroll Down <ESC>D
  - Scroll display down one line.

https://wiki.plecko.hr/ Printed on 2025/04/04 08:29

- Scroll Up <ESC>M
  - Scroll display up one line.

## **Tab Control**

- Set Tab <ESC>H
  - Sets a tab at the current position.
- Clear Tab <ESC>[q
  - Clears tab at the current position.
- Clear All Tabs <ESC>[3g
  - Clears all tabs.

# **Erasing Text**

- Erase End of Line <ESC>[K
  - Erases from the current cursor position to the end of the current line.
- Erase Start of Line <ESC>[1K
  - Erases from the current cursor position to the start of the current line.
- Erase Line <ESC>[2K
  - Erases the entire current line.
- Erase Down <ESC>[]
  - Erases the screen from the current line down to the bottom of the screen.
- Erase Up <ESC>[1]
  - Erases the screen from the current line up to the top of the screen.
- Erase Screen <ESC>[2]
  - Erases the screen with the background colour and moves the cursor to home.

## **Printing**

Some terminals support local printing:

- Print Screen <ESC>[i
  - Print the current screen.
- Print Line <ESC>[1i
  - Print the current line.
- Stop Print Log <ESC>[4i
  - Disable log.
- Start Print Log <ESC>[5i
  - Start log; all received text is echoed to a printer.

# **Define Key**

- Set Key Definition <ESC>[{key};"{string}"p
  - Associates a string of text to a keyboard key. {key} indicates the key by its ASCII value in decimal.

# **Set Display Attributes**

- Set Attribute Mode <ESC>[{attr1};...;{attrn}m
  - Sets multiple display attribute settings. The following lists standard attributes:
- O Reset all attributes
- 1 Bright
- 2 Dim
- 4 Underscore
- 5 Blink
- 7 Reverse
- 8 Hidden

### Foreground Colours

- 30 Black
- 31 Red
- 32 Green
- 33 Yellow
- 34 Blue
- 35 Magenta
- 36 Cyan
- 37 White

### Background Colours

- 40 Black
- 41 Red
- 42 Green
- 43 Yellow
- 44 Blue
- 45 Magenta
- 46 Cyan
- 47 White

### From:

https://wiki.plecko.hr/ - Eureka Moment

#### Permanent link:

https://wiki.plecko.hr/doku.php?id=development:php:cli\_cursor

Last update: 2019/10/31 09:04



https://wiki.plecko.hr/ Printed on 2025/04/04 08:29