Cursor controll in PHP cli scripts

Controll cursor in CLI scripts by echoing ANSI characters

echo "\033[100D";

Many computer terminals and terminal emulators support colour and cursor control through a system of escape sequences. One such standard is commonly referred to as ANSI Colour. Several terminal specifications are based on the ANSI colour standard, including VT100.

The following is a partial listing of the VT100 control set.

<ESC> represents the ASCII "escape" character, 0x1B. Bracketed tags represent modifiable decimal parameters; eg. {ROW} would be replaced by a row number.

Device Status

The following codes are used for reporting terminal/display settings, and vary depending on the implementation:

- Query Device Code <ESC>[c
 - Requests a Report Device Code response from the device.
- Report Device Code <ESC>[{code}0c
 - Generated by the device in response to Query Device Code request.
- Query Device Status <ESC>[5n
 - Requests a Report Device Status response from the device.
- Report Device OK <ESC>[0n
 - Generated by the device in response to a Query Device Status request; indicates that device is functioning correctly.
- Report Device Failure <ESC>[3n
 - Generated by the device in response to a Query Device Status request; indicates that device is functioning improperly.
- Query Cursor Position <ESC>[6n
 - Requests a Report Cursor Position response from the device.
- Report Cursor Position <ESC>[{ROW};{COLUMN}R
 - Generated by the device in response to a Query Cursor Position request; reports current cursor position.

Terminal Setup

The h and I codes are used for setting terminal/display mode, and vary depending on the implementation. Line Wrap is one of the few setup codes that tend to be used consistently:

- Reset Device <ESC>c
 - Reset all terminal settings to default.
- Enable Line Wrap <ESC>[7h

- Text wraps to next line if longer than the length of the display area.
- Disable Line Wrap <ESC>[7]
 - Disables line wrapping.

Fonts

Some terminals support multiple fonts: normal/bold, swiss/italic, etc. There are a variety of special codes for certain terminals; the following are fairly standard:

- Font Set G0 <ESC>(
 - Set default font.
- Font Set G1 <ESC>)
 - Set alternate font.

Cursor Control

- Cursor Home <ESC>[{ROW};{COLUMN}H
 - Sets the cursor position where subsequent text will begin. If no row/column parameters are provided (ie. <ESC>[H), the cursor will move to the home position, at the upper left of the screen.
- Cursor Up <ESC>[{COUNT}A
 - Moves the cursor up by COUNT rows; the default count is 1.
- Cursor Down <ESC>[{COUNT}B
 - Moves the cursor down by COUNT rows; the default count is 1.
- Cursor Forward <ESC>[{COUNT}C
 - Moves the cursor forward by COUNT columns; the default count is 1.
- Cursor Backward <ESC>[{COUNT}D
 - Moves the cursor backward by COUNT columns; the default count is 1.
- Force Cursor Position <ESC>[{ROW};{COLUMN}f
 - Identical to Cursor Home.
- Save Cursor <ESC>[s
 - Save current cursor position.
- Unsave Cursor <ESC>[u
 - Restores cursor position after a Save Cursor.
- Save Cursor & Attrs < ESC > 7
 - Save current cursor position.
- Restore Cursor & Attrs <ESC>8
 - Restores cursor position after a Save Cursor.

Scrolling

- Scroll Screen <ESC>[r
 - Enable scrolling for entire display.
- Scroll Screen <ESC>[{start};{end}r
 - Enable scrolling from row {start} to row {end}.
- Scroll Down <ESC>D
 - Scroll display down one line.

https://wiki.plecko.hr/ Printed on 2025/10/16 04:00

- Scroll Up <ESC>M
 - Scroll display up one line.

Tab Control

- Set Tab <ESC>H
 - Sets a tab at the current position.
- Clear Tab <ESC>[q
 - Clears tab at the current position.
- Clear All Tabs <ESC>[3g
 - Clears all tabs.

Erasing Text

- Erase End of Line <ESC>[K
 - Erases from the current cursor position to the end of the current line.
- Erase Start of Line <ESC>[1K
 - Erases from the current cursor position to the start of the current line.
- Erase Line <ESC>[2K
 - Erases the entire current line.
- Erase Down <ESC>[]
 - Erases the screen from the current line down to the bottom of the screen.
- Erase Up <ESC>[1]
 - Erases the screen from the current line up to the top of the screen.
- Erase Screen <ESC>[2]
 - Erases the screen with the background colour and moves the cursor to home.

Printing

Some terminals support local printing:

- Print Screen <ESC>[i
 - Print the current screen.
- Print Line <ESC>[1i
 - Print the current line.
- Stop Print Log <ESC>[4i
 - Disable log.
- Start Print Log <ESC>[5i
 - Start log; all received text is echoed to a printer.

Define Key

- Set Key Definition <ESC>[{key};"{string}"p
 - Associates a string of text to a keyboard key. {key} indicates the key by its ASCII value in decimal.

Set Display Attributes

- Set Attribute Mode <ESC>[{attr1};...;{attrn}m
 - Sets multiple display attribute settings. The following lists standard attributes:
- O Reset all attributes
- 1 Bright
- 2 Dim
- 4 Underscore
- 5 Blink
- 7 Reverse
- 8 Hidden

Foreground Colours

- 30 Black
- 31 Red
- 32 Green
- 33 Yellow
- 34 Blue
- 35 Magenta
- 36 Cyan
- 37 White

Background Colours

- 40 Black
- 41 Red
- 42 Green
- 43 Yellow
- 44 Blue
- 45 Magenta
- 46 Cyan
- 47 White

From:

https://wiki.plecko.hr/ - Eureka Moment

Permanent link:

https://wiki.plecko.hr/doku.php?id=development:php:cli_cursor

Last update: 2019/10/31 09:04



https://wiki.plecko.hr/ Printed on 2025/10/16 04:00