Create partitions using CLI on linux

First and foremost:

!! WARNING !!

These commands are EXAMPLES. DELETING partitions, MODIFYING and FORMATTING filesystems destroys data and/or may prevent your machine from booting. Make backups. Use at own risk. Try on a machine you don't mind losing all data on. caveat admin.

To quickly set up a drive up as a single ext4 partition... View detected devices of class "DISK"

```
lshw -C disk
```

View existing partition table(s)

```
fdisk -l
```

Edit the partition table for my chosen device (in this case, "sdx")

fdisk /dev/sdx

Within FDISK, press:

```
d ...to delete the current partition
n ...to create a new partition
p ...to specify it as a PRIMARY partition
1 ...to set it as the 1ST primary partition
w ...to write the changes.
```

Display the new partition table:

```
fdisk -l
```

Format the new partition's filesystem as type ext4

```
mkfs -t ext4 /dev/sdx1
```

Create a new directory where the new drive will mount into:

```
mkdir /storage
mount /dev/sdx1 /storage
```

TUNING Remove reserved blocks (i.e. set to 0%), since this drive is just for user data

```
tune2fs -m 0 /dev/sdx1
```

Since server is on UPS, Set write-back so apps don't wait for actual disk writes

```
tune2fs -o journal data writeback /dev/sdx1
```

Mount at boot up using /etc/fstab and also set write-back policy

```
vi /etc/fstab
```

Find (or add) the relevant line in fstab for your drive. Parameters in fstab are separated by white space, for example the drive described above might appear as:

```
/dev/sdx1 /storage ext4 relatime,errors=remount-ro 0 1
```

- The first parameter identifies the partition (either by /dev/ or a long UUID);
- The second parameter is the path the partition will be mounted to;
- Third is the filesystem type;
- The fourth parameter contains the options;
- Fifth is the dump schedule for backups; and,
- The sixth parameter is pass-number (used to control fsck order).

Change the options (4th parameter) to:

```
noatime, nodiratime, data=writeback, barrier=0, nobh, errors=remount-ro
```

Reboot to check that everything went well. Remember these commands are destructive! Have backups and be careful!

Speedy

```
su@fs:~$ lsblk
NAME
       MAJ:MIN RM SIZE RO TYPE MOUNTPOINT
loop0
               0 55.4M 1 loop /snap/core18/2846
         7:0
loop1
         7:1
                0 55.4M 1 loop /snap/core18/2855
               0 44.4M
                        1 loop /snap/snapd/23545
loop2
        7:2
loop3
        7:3
                0 91.9M
                        1 loop /snap/lxd/32662
loop4
        7:4

    63.7M

                        1 loop /snap/core20/2434
loop5
        7:5
                0 44.5M
                        1 loop /snap/snapd/23771
loop6
        7:6
                0 63.8M
                        1 loop /snap/core20/2496
                0 91.9M
loop7
        7:7
                        1 loop /snap/lxd/29619
                    32G
                        0 disk
sda
        8:0
                0
                   512M
⊢sda1
        8:1
                0
                        part /boot/efi
                0 31.5G
∟sda2
        8:2
                        part /
        8:16
                  3.5T
                         0 disk
sdb
                0
∟sdb1
        8:17
               0
                   3.5T
                         0 part /shared
sdc
        8:32
                     1T
                         0 disk
                0
∟sdc1
        8:33
                0 1024G
                         part
                1 1024M
sr0
        11:0
                         0 rom
su@fs:~$ sudo mkfs -t ext4 /dev/sdc1
$ fdisk /dev/sdc
n
W
```

https://wiki.plecko.hr/ Printed on 2025/04/12 11:43

```
su@fs:~$ mkfs -t ext4 /dev/sdc1
$ blkid
/dev/sda1: UUID="A3E4-5689" TYPE="vfat" PARTUUID="e7003b9a-
af04-4f3c-987e-f18603949308"
/dev/sda2: UUID="56b502b1-9df0-4cb7-a510-246957938839" TYPE="ext4"
PARTUUID="7dcb6a1f-0925-4f00-9c22-4643f8e6988a"
/dev/sdb1: UUID="3b02d9b1-940e-46a0-9b48-b25a5f88e329" TYPE="ext4"
PARTUUID="1df82f8c-22e8-4c4b-91cc-7921fcb8705f"
/dev/loop0: TYPE="squashfs"
/dev/loop1: TYPE="squashfs"
/dev/loop2: TYPE="squashfs"
/dev/loop3: TYPE="squashfs"
/dev/loop4: TYPE="squashfs"
/dev/loop5: TYPE="squashfs"
/dev/loop6: TYPE="squashfs"
/dev/loop7: TYPE="squashfs"
/dev/sdc1: UUID="6028d925-83c5-4fd3-9e88-3ec1c60f8073" TYPE="ext4"
PARTUUID="7bd58fd1-01"
su@fs:~$ vim /etc/fstab
/dev/disk/by-uuid/6028d925-83c5-4fd3-9e88-3ec1c60f8073 /shared/pub ext4
defaults, noacl 0 0
su@fs:~$ mount -a
```

From:

https://wiki.plecko.hr/ - Eureka Moment

Permanent link:

https://wiki.plecko.hr/doku.php?id=linux:shell_commands:fdisk

Last update: 2025/04/09 12:42

