Enable and disable Windows Features on Server 2012 R2 Core

So, you have installed Windows Server 2012 R2 Core and are determined to manage it without using any GUI tools. Very enthusiastic. I'd prefer to use Server Manager from a remote machine, but what the hell. Hit the keyboard.

The first thing to do is to list available features and their current state by using the 'dism' command. The output also reveals the percise feature names.

dism /online /get-features /format:table

You will get a table-like output like in the image:

Select Administrator: C:\Windows\System32\cmd.exe –	
C:\windows\system32>dism /online /get-features /format:table	
Deployment Image Servicing and Management tool Version: 6.3.9600.16384	
Image Version: 6.3.9600.16384	
Features listing for package : Microsoft-Windows-ServerCore-Package~31bf3856ad364e35~amd64~~6.3.9600 .16384	
Feature Name	State
NetFx4ServerFeatures NetFx4 NetFx4Extended-ASPNET45 MicrosoftWindowsPowerShellRoot MicrosoftWindowsPowerShell ServerCore-FullServer IIS-WebServer IIS-WebServer IIS-CommonHtpFeatures IIS-Security IIS-Security IIS-Security IIS-StaticContent IIS-DefaultDocument IIS-DefaultDocument IIS-DirectoryBrowsing IIS-HttpErrors IIS-ApplicationDevelopment IIS-ApplicationDevelopment IIS-NetFxExtensibility IIS-NetFxExtensibility IIS-NetFxExtensibility IIS-NetFxExtensibility IIS-NetFxExtensibility IIS-Applfilter IIS-ASPNE1 IIS-ASPNE1 IIS-ASPNE1 IIS-ASPNE145 IIS-ServerSideIncludes IIS-ASPNE15 IIS-ServerSideIncludes IIS-LoggingLibraries IIS-LoggingLibraries IIS-RequestMonitor	Enabled Enabled Disabled Enabled Enabled Disabled


For additional feature information, use (eg. for SmbDirect)

Dism /online /get-featureInfo /featureName:SmbDirect

To list installed packets, use:

dism /online /get-packages /format:table

You will get table-like output like in the image:



```
For aditional feature information, use (eg. for
Package_for_KB2995004~31bf3856ad364e35~amd64~~6.3.1.0):
```

```
dism /online /get-packageinfo
/packagename:Package for KB2995004~31bf3856ad364e35~amd64~~6.3.1.0
```

To enable or disable features, use (eg. for SmbDirect):

```
Dism /online /enable-feature /featurename:SmbDirect
Dism /online /disable-feature /featurename:SmbDirect
```

Multiple /featureName arguments can be used if the features are components in the same parent package. Add /remove to remove the payloads without removing the feature's manifest from the image. Once the payload is removed, a feature will have the status, 'Disabled with Payload Removed.' and can be restored and enabled using /Enable-Feature with the /Source option.

From: https://wiki.plecko.hr/ - Eureka Moment

Permanent link: https://wiki.plecko.hr/doku.php?id=windows:server_os:core_features



Last update: 2019/10/31 09:06