Setup a Domain Controller with Windows 2016 Server Core

Setup static IP Open Powershell Install ADDS

```
Install-WindowsFeature AD-Domain-Services
#or
Install-WindowsFeature AD-Domain-Services -IncludeManagementTools
```

Commands:

- Add-ADDSReadOnlyDomainControllerAccount Install read only domain controller
- Install-ADDSDomain Install first domain controller in a child or tree domain
- Install-ADDSDomainController Install additional domain controller in domain
- Install-ADDSForest Install first domain controller in new forest
- **Test-ADDSDomainControllerInstallation** Verify prerequisites to install additional domain controller in domain
- Test-ADDSDomainControllerUninstallation Uninstall AD services from server
- **Test-ADDSDomainInstallation** Verify prerequisites to install first domain controller in a child or tree domain
- Test-ADDSForestInstallation Install first domain controller in new forest
- Test-ADDSReadOnlyDomainControllAccountCreation Verify prerequisites to install read only domain controller
- Uninstall-ADDSDomainController Uninstall the domain controller from server

Installing the First Domain Controller in Forest

This will install the basic features and functions, however, if you want to install a customised setup – which I assume you would want to do – in a proper business environment, I will provide a sample setup for you to follow. I will lay this out line per line, to make for easy reading, but when you are passing the parameters, please be sure not to break lines anywhere. The line breaks in my example are just for readability:

```
Install-ADDSForest
-CreateDnsDelegation:$false
-DatabasePath "C:\Windows\NTDS"
-DomainMode "Win2012R2" //use integer 7 for Win2016
-DomainName "contoso.com"
-DomainNetbiosName "CONTOSO"
-ForestMode "Win2012R2" //use integer 7 for Win2016
-InstallDns:$true
-LogPath "C:\Windows\NTDS"
-NoRebootOnCompletion:$false
-SysvolPath "C:\Windows\SYSVOL"
-Force:$true
```

Installing the Additional Domain Controller in domain

Install-ADDSDomainController -DomainName contoso.com -InstallDNS:\$True
_Credential (Get-Credential)

Transfering roles to the new server

- 1. Open ADUC
- 2. Change domain controller to the desired DC
- 3. Open 'Operations Masters'
- 4. Click 'Change' on all roles

Joining server into the domain

add-computer -DomainName contoso.com -Credential (Get-Credential)

Subdomain

Install-ADDSDomain -NewDomainName sub -ParentDomainName contoso.com InstallDNS -CreateDNSDelegation -DomainMode 7 -SafeModeAdministratorPassword
(Get-Credentials) -Credentials (Get-Credentials)

From: https://wiki.plecko.hr/ - **Eureka Moment**

Permanent link: https://wiki.plecko.hr/doku.php?id=windows:powershell_commands:add_core_addc_2016

Last update: 2019/10/31 09:06

